

## Summary

In version 7.5, to import data from script using a pre-defined Import Wizard Filter (.OIF), one had to first load the ImportWiz workspace to ensure all necessary OC files are loaded and compiled.

In Origin 8, it is no longer necessary to load the ImportWiz workspace. Please see this [Origin C wiki page](#) for details on how to call your own OC function to perform the import from script using a pre-defined filter.

Also, in Origin 8 one could simply use the `impFile` X-function from script to import a file using a pre-defined filter. In this case there is no need to write any OC code. Please see this [Labtalk Guide wiki page](#) for details.